

Application Configuration

See: [Best Practices - Fedora Configuration](#)

Four means of deploying Fedora 4 have been verified

- Each of these deployment approaches has its own way of setting System Properties.

On Debian Linux systems, the typical way of setting System Properties is to update the following file:

Within that file, new properties can be added per the example below:

Additional information regarding the configuration of System Properties in Tomcat 7 can be found [here](#).

Alternatively on Windows systems you can set the following file:

Within that file, new properties can be added per the example below:

When starting up tomcat on windows if you receive an error like the following it may be necessary to include a **fcrepo.ispn.repo.cache** like above.

On Debian Linux systems, one way of setting System Properties is to update the following file:

Within that file, new properties can be added per the example below (note the use of `JAVA_OPTIONS` instead of `JAVA_OPTS`):

Additional information regarding the configuration of System Properties in Jetty 9 can be found [here](#).

Windows notes

Alternatively on Windows systems you can set the following file:

```
{JETTY_DIST}/start.ini
```

Within that file, new properties can be added per the example below:

```
--exec  
-Dfcrepo.home=/mnt/fedora-data
```

Maven jetty:run

System Properties can be set when using the Maven jetty:run plugin by passing them per the example below:

```
mvn -Dfcrepo.home=/mnt/fedora-data jetty:run
```

One-Click Run

If the One-Click Run is started from the command line, System Properties can be passed in per the example below:

```
java -Dfcrepo.home=/mnt/fedora-data -jar fcrepo-webapp-jetty-console.war
```

Configuration Elements

There are a number of configuration elements that can be optionally be set when starting the Fedora 4 web-application. No configuration elements are required to be set, as they all default values (noted below within brackets: <>).

```
fcrepo.home=<cwd/fcrepo4-data>
```

This can be set to a path (relative to the current working directory or absolute) to which Fedora repository content will be written. Any of the Modeshape and Infinispan configuration options below will default to being within this folder if unset or if set to a relative path. If unset, content will be put in the "fcrepo4-data" directory within the current working directory.

```
fcrepo.modeshape.configuration=<classpath:/config/repository.json | file:/path/to/repository.json>
```

This specifies the configuration for the underlying Modeshape repository. See other available options for this value within the [source tree](#). The default file is located within the WAR file under WEB-INF/classes/config.

```
fcrepo.ispn.configuration=<config/infinispan.xml>
```

This specifies the underlying Infinispan cache configuration. This value has a tested default set in the *modeshape.json* file mentioned above; and therefore, can usually be left as is. The default file is located within the WAR file under WEB-INF/classes/config.

```
java.io.tmpdir=</tmp on Linux, $TMPDIR on MacOSX, and %TEMP% on Windows>
```

This specifies the directory for writing temp files. You may need to set this property to a larger disk/filesystem to upload large files, particularly on Linux where /tmp is sometimes on a small partition.

```
fcrepo.jms.baseUrl=<http://localhost:8080/fcrepo/rest>
```

This specifies the baseUrl to use when generating JMS messages. You can specify the hostname with or without port and with or without path. If your system is behind a NAT firewall you may need this to avoid your message consumers trying to access the system on an invalid port. If this system property is not set, the host, port and context from the user's request will be used in the emitted JMS messages.

Modeshape and Infinispan

The Modeshape and Infinispan configurations mentioned above have a number of more detailed configuration elements that can optionally be set. To see exactly which elements are available to be set, inspect the *repository.json* and *infinispan.xml* files specified above. Those files can be browsed in the source tree in:

- the ModeShape [configuration directories](#) and,
- the Infinispan [configuration directories](#).

Some common elements for Modeshape and Infinispan relate to the directories in which application information is persisted. As mentioned above, if no *fcrepo.home* property is set then application information will be persisted under the directory "fcrepo4-data" in the application's current working directory. There will then be several directories within "fcrepo4-data" that are named by default with the name of the property that can be set to configure each of those directories.

Below are some common examples of these directories:

```
fcrepo.ispn.repo.cache
```

Contains the serialized repository resource properties.

```
fcrepo.modeshape.index.directory
```

Contains the internal Lucene index used by Modeshape/Admin Search.

```
fcrepo.activemq.directory
```

Contains the reliable messaging information maintained by ActiveMQ.

```
com.arjuna.ats.arjuna.common.ObjectStoreEnvironmentBean.default.objectStoreDir  
com.arjuna.ats.arjuna.objectstore.objectStoreDir
```

Contain [JBoss JTA](#) transaction engine artifacts.

Configuration Chain

The standard configuration chain is as follows:

1. **fcrepo4/fcrepo-webapp/src/main/webapp/WEB-INF/web.xml** contains a **context-param** element with **param-name** "contextConfigLocation". The **param-value** points to your spring configuration file, usually a path like **WEB-INF/classes/*.xml**
2. One of your spring configuration files is **repo.xml** that contains a property **repositoryConfiguration** defining the location of your **repository.json**
3. **fedora-node-types.cnd** is defined in **repository.json**