

Change page text (JSP)

Contents

1 [Change page text](#)

1.1 [Files:](#)

1.1.1 [Instructions:](#)

1.1.2 [Notes:](#)

Change page text

This page describes how to change text on a page of the JSPUI.

Files:

The location of the files you'll want to edit depend on which version of DSpace you are using, as the location of the primary JSP folder has changed in DSpace over the years.

- **DSpace 3.0 or above**
 - Messages file: [dspace-source]/dspace-api/src/main/resources/Messages.properties
 - JSP folder: [dspace-source]/dspace-jspui/src/main/webapp/ (*JSP containing the text you want to change*)
- **DSpace 1.5.0 through 1.8.2**
 - Messages file: [dspace-source]/dspace-api/src/main/resources/Messages.properties
 - JSP folder: [dspace-source]/dspace-jspui/dspace-jspui-webapp/src/main/webapp/ (*JSP containing the text you want to change*)
- **DSpace 1.4.2 and earlier versions**
 - Messages file: [dspace-source]/config/language-packs/Messages.properties
 - JSP folder: [dspace-source]/jsp/ (*JSP containing the text you want to change*)

Instructions:

1. Open Messages.properties and search for the text you wish to change.
 - Note: Messages.properties contains pairs of "keys" and "values". For example:

```
jsp.home.search1 = Search
```

2. Generally speaking, the "key" usually refers to the location of the JSP on which this text resides (e.g. `jsp.home.search` is "search-related" text displayed in `home.jsp`)
3. If Messages.properties contains that text in more than one place, open the relevant JSP and find the `key` attribute of the appropriate `<fmt:message>` element. For example:

```
<fmt:message key="jsp.home.search1" />
```

4. Change the text (that corresponds to the key) in Messages.properties.
5. Perform the steps in [Rebuild DSpace](#).
OR
Follow the steps in [FAQs](#) to reflect the changes without doing rebuild.

Notes:

1. When adding or modifying text in Messages.properties, be very careful that you have automatic word-wrap turned off in your text editor! The "key" and its corresponding "value" must always be on the same line within Messages.properties (e.g.) This is NOT a valid entry in Messages.properties:

```
jsp.community-home.heading1 = This is a really long heading  
which actually gets wrapped automatically by my text editor  
so that it ends up on three separate lines.
```